

# Mail Server


## How to add my domain as sender?

In order to send from your own domain you need to delegate it to nameservers:

ns1.flynet.pro  
ns2.flynet.pro

Go to Client area bill.flynet.pro -> Products/Services -> [VPS hosting](#) -> select string with needed server -> "Instructions" button -> find 'Hestia LAMP control panel' chapter on instructions page

Go to Hestia LAMP control panel - > Web -> 'Add Web Domain' button



The screenshot shows the Hestia LAMP control panel interface. At the top, there is a navigation bar with 'Records', 'Files', 'Logs', and 'Statistics'. Below this is a dashboard with several sections: 'USERS' (1 user, 0 suspended), 'WEB' (1 domain, 0 aliases), 'DNS' (1 zone, 17 records), 'MAIL' (1 domain, 6 accounts), 'DB' (1 database), and 'CRON' (11 jobs). The main content area is titled 'Add Web Domain' and contains a red warning box: 'It is strongly advised to create a standard user account before adding web domains to the server due to the increased privileges the admin account possesses and potential security risks.' Below the warning, there are input fields for 'Domain' (containing 'domain.com') and 'IP Address' (containing '45.95.30.123'). There are two checked checkboxes: 'Create DNS zone' and 'Enable mail for this domain'. At the bottom of the form is an 'Advanced Options' button and a 'Save' button.

Put your domain name in 'Domain' field  
Check 'Create DNS zone' and 'Enable mail for this domain' checkboxes  
Press 'Save' button

Go to Hestia LAMP control panel - > Mail -> your just created domain -> 'Add mail account' button

# Mail Server

The screenshot shows the Hestia Mail Server control panel. At the top, there is a navigation bar with 'Records', 'Files', 'Logs', and 'Statistics'. Below this, there are several status indicators: 'USERS' (1 user, 0 suspended), 'WEB' (1 domain, 0 aliases), 'DNS' (1 zone, 17 records), 'MAIL' (2 domains, 6 accounts), 'DB' (1 database), and 'CRON' (11 jobs). The main content area is titled 'Add Mail Account' and contains the following fields and options:

- Domain:** A text input field containing 'domain.com'.
- Account:** A text input field containing 'user'.
- Password / Generate:** A text input field containing a generated password '7muCGHcgDbeLRy5'. Below it, a note states: 'Your password must have at least:
  - 8 characters long
  - 1 uppercase & 1 lowercase character
  - 1 number
- Advanced Options:** A button with a dropdown arrow.
- Email login credentials to:** A text input field.
- USE DOMAIN NAME:** A summary box showing the following details:
  - Username: user@domain.com
  - Password: 7muCGHcgDbeLRy5
  - IMAP Hostname: mail.domain.com
  - IMAP Port: 143
  - IMAP Security: STARTTLS
  - IMAP Authentication Method: Normal Password
  - SMTP Hostname: mail.domain.com
  - SMTP Port: 587
  - SMTP Security: STARTTLS
  - SMTP Authentication Method: Normal Password
  - Webmail Alias: http://webmail.domain.com

Put username  
Generate password  
Press 'Save' button

Now you can use just created SMTP credentials in any SMTP mailer (external too).

For better delivery rate create DKIM sign for domain  
Go to Hestia LAMP control panel -> Mail -> your just created domain -> 'Edit mail domain' icon (pencil) -> check 'DKIM' checkbox - press 'Save' button

Unique solution ID: #1004  
Author: leksei  
Last update: 2021-10-04 09:03